

# Programming Proverbs

- 6. “Use procedures (methods or functions).”
- Henry F. Ledgard, “Programming Proverbs: Principles of Good Programming with Numerous Examples to Improve Programming Style and Proficiency”, (Hayden Computer Programming Series), Hayden Book Company, 1st edition, ISBN-13: 978-0810455221, December 1975.

## If your ioquake is not allowing Pylego to disableAI

- then you need to download and install this tarball

```
$ ssh mcgreg.comp.glam.ac.uk
<enter your linux password>
$ cd $HOME/Sandpit
$ wget http://floppsie.comp.glam.ac.uk/download/c/ioquake-20161025.tar.gz
$ rm -rf ioquake-latest
$ tar xzf ioquake-20161025.tar.gz
$ exit
# your command line is back on the client
$ cd $HOME/Sandpit/ioquake-latest3/ioquake
$ ./compilequake
```

- please only do the above if you are experiencing problems getting pylego to connect

## python-bot/bot-legoman/botfiles/bots/botlib.py

- enumerated type of rpc meta types:


```
CHAR, WEIGHT, AI, BASIC, GOAL, COMMANDS = range(1, 7)
```

- CHAR
  - the packets contain characteristic information
- WEIGHT
  - not yet implemented, but it will upload weightings for weapons
- AI
  - codes are only just being implemented they consist of new commands necessary to enable Python to connect to ioquake

## `python-bot/bot-legoman/botfiles/bots/botlib.py`

- the following meta types correspond to the AI layered architecture in ioquake (they should be extended when time permits)
  
- BASIC
  - basic actions which we can tell the bot to do (jump, crouch, fire)
  
- GOAL
  - interface to the goal logic of the AI engine.
  
- COMMANDS
  - give bot commands (as a team leader)

# python-bot/bot-legoman/botfiles/bots/botlib.py



```
# AI codes
SKILL, CONT = range(1, 3)
# BASIC codes
JUMP, CROUCH, FIRE = range(1, 4)
```

## class bot: \_\_init\_\_

```
def __init__ (self, server, port):  
    global s  
  
    self.init_chars()  
    s = socket(AF_INET, SOCK_STREAM)  
    print "bot trying to connect to the server",  
    while True:  
        try:  
            s.connect((server, port))  
            break  
        except:  
            print ".",  
            sys.stdout.flush()  
            time.sleep(1)  
    print "bot connected"
```

## `class bot: init_chars (self)`

- initialises all the characteristics which can be altered in the Python bot
- no data is sent to the ioquake3 server at this point
- the `botlib.py` is told the characteristic name, type, code, max, min values

# Python bot

- recall our bot code can be simplified to



# Python bot

```
id = botlib.bot("localhost", 7000)
print "hello world, python is alive in Quake 3"
id.defaults()
print "bot is now active!"
id.disableAI()
while True:
    print "trying to crouch"
    id.crouch()
    print "in crouch position"
    time.sleep(1)
    id.jump()
    print "in jump position"
    time.sleep(1)
    id.fire()
    print "fire"
    time.sleep(1)
```

## class bot: defaults

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](#)

```
def defaults(self):  
    if self.skill() == 1:  
        self.c_name.set("Pylego")  
        self.c_gender.set("male")  
        self.c_attack_skill.set(0.9)  
        self.c_weaponweights.set("bots/Easy_w.c")  
        self.c_aim_skill.set(0.95)  
    ...
```

## class bot: skill

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](https://github.com/ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py)

```
def skill (self):  
    """ this must be the next method called after __init__ """  
    print "sending skill"  
    return callBI(AI, SKILL)
```

## callBI

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](#)

```
#
# callBI - makes a call and returns an byte integer.
#

def callBI (c1, c2):
    global s

    p = makeHeader(struct.pack("B", c1), struct.pack("B", c2))
    for i in p:
        print ord(i),
    print
    s.send(p)
    return getReturnByte(s)
```

■ the `struct.pack("B", c1)` packs a Python integer `c1` into a byte

# makeHeader

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](#)

```
#  
# makeHeader - creates the rpc header  
#  
  
def makeHeader (meta, data = ""):  
    s = meta + data  
    return prependLength(s)
```

# makeHeader

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](#)

```
#  
# prependLength - places the length byte at the start of the packet  
#  
  
def prependLength (s):  
    print "prepending length of", len(s)  
    return struct.pack("B", len(s)) + s
```

# getReturnByte

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](https://github.com/legoman/python-bot/blob/master/botfiles/bots/botlib.py)

```
#
# getReturnByte - defensively receives the return byte
#

def getReturnByte (s):
    p = ""
    while True:
        p = s.recv(1)
        if len(p) == 1:
            print "received packet of length", ord(p[0])
            break
    if ord(p[0]) == 2:
        while True:
            p = s.recv(1)
            if len(p) == 1:
                break
        printf("byte returned has value %d\n", struct.unpack("B", p)[0])
        return struct.unpack("B", p)[0]
    else:
        printf("expecting length of 2 received %d\n", ord(p[0]))
    return 0
```

## Protocol

- first byte contains the packet length
- so the above code expects two bytes
  - a length byte of value, 2
  - the second byte is the data byte which is returned as an integer



## setchar - low level function to send a characteristic to the ioquake3 server

■ [ioquake-latest/python-bot/bot-legoman/botfiles/bots/botlib.py](#)

```
#
# setchar - send value using code, type, value to the server
#

def setchar (code, type, value):
    global s

    print "sending characteristic", code, type, value
    c = struct.pack("B", CHAR)
    d = struct.pack("B", code)
    if type=="int":
        s.send(makeHeader(c, d+struct.pack("i", value)))
    elif type=="float":
        s.send(makeHeader(c, d+struct.pack("f", value)))
    elif type=="string":
        s.send(makeHeader(c, d+struct.pack(("%ds" % (len(value)+1)), value)))
    if not getReturnBoolean(s):
        print "failed to set characteristic", code, "type", type, "value", value
```

## ioquake3 server must match these rpc requests

- examine the file `$HOME/Sandpit/ioquake-latest/ioquake3/code/botlib/be_ai_py.c` and in particular start by understanding the function `initPy`
- then examine `testFor` and `waitForCont`
- notice that both are very similar
- notice that `execFunction` is called to handle the rpc
  - a return packet is sent back provided that the `execFunction` populated the return buffer
- understand that the rpc server is a state machine
  - `py->state` is set to `pyInit`, `pyOut`, `pyIn`

# testFor

■ [ioquake-latest/ioquake3/code/botlib/be\\_ai\\_py.c](#)

```
int testFor (py_bot_t *py)
{
    if (py->state == pyInit) {
        py->in = 0;
        py->out = 0;
        py->used = 0;
        py->state = pyIn;
    }
    if (py->state == pyIn) {
        if (getPacket(py, qtrue))
            py->state = pyInit;
        else
            return qfalse;
        execFunction(py);
    }
}
```

# testFor

■ [ioquake-latest/ioquake3/code/botlib/be\\_ai\\_py.c](#)

```
if (py->state == pyOut) {
    if (putPacket(py, qtrue)) {
        py->out = 0;
        py->used = 0;
        py->state = pyInit;
    } else
        return qfalse;
}
return qtrue;
}
```

# Tutorial

- read these notes carefully and open up emacs and read the actual code being discussed
- take a pen and paper and now create your own notes detailing how a Python call to the method `ourself` is executed
  - your notes should include both client and server activity