

Tutorial: Penguin Tower

- is a multiplayer 2 dimensional game
 - inspired by [Morloc Tower](http://www.mobygames.com/game/dunjonquest-morlocs-tower) `<http://www.mobygames.com/game/dunjonquest-morlocs-tower>` although Penguin Tower is very different
- however the screen layout and many of the key commands are the same

Tutorial: Penguin Tower

- you can download a copy of the game from [here](http://floppsie.comp.glam.ac.uk/download/penguin-tower/penguin-tower-2.0.tar.gz) `<http://floppsie.comp.glam.ac.uk/download/penguin-tower/penguin-tower-2.0.tar.gz>`.
- you then need to extract the archive using the following command line:

```
$ mkdir $HOME/Sandpit  
$ cd $HOME/Sandpit  
$ wget http://floppsie.comp.glam.ac.uk/download/penguin-tower/penguin-tower-2.0.tar.gz  
$ tar zxvf penguin-tower-2.0.tar.gz
```

Creating important directories

- these directories need to be created before penguin tower can be built

```
$ mkdir -p $HOME/Sandpit  
$ cd $HOME/Sandpit  
$ mkdir -p $HOME/opt/bin  
$ mkdir build-ptower
```

Building Penguin Tower

- you should be able to build it by typing:

```
$ cd $HOME/Sandpit
$ cd build-ptower
$ ../penguin-tower-2.0/configure --prefix=$HOME/opt
$ make
$ cd ..
```

- you need to check that the make program above exited with no error messages
- note the build will recreate all images in the build directory.

Installing your own copy of Penguin Tower

- you can install your own copy of Penguin Tower into your directory (`$HOME/opt`) specified by the `--prefix` to the `./configure` command

```
$ cd $HOME/Sandpit  
$ cd build-ptower  
$ make install  
$ cd ..
```

Penguin Tower keyboard controls

- [keyboard controls](#) `<ptower.html>`.

Configure notes

- you only need to execute `./penguin-tower-2.0/configure --prefix=$HOME/opt` once ever in this directory (unless you modify the package)
- check out the documentation [here](#) (`ptower.html`).

Configure notes

- you can also run the system installed version by typing:

- `$ penguin-tower mcgreg.comp.glam.ac.uk:7000`

Running your own Penguin Tower server

- can be done by opening a terminal and typing the following:

```
$ cd  
$ ./opt/bin/ptower-server ./opt/share/ptower/maps/star
```

- to stop the server, type `^C` (press down the control key and then press the `c` key, now release both keys)
- there are a number of maps in the `$HOME/opt/share/penguin-tower/maps` directory
 - `m1`, `star` and `glover`
 - `star` is the smallest (5 rooms)

Tutorial work

- examine the map file format in the maps directory
 - try making a simple change and running Penguin Tower again
- here is the documentation to [Penguin Tower](http://floppsie.comp.glam.ac.uk/Southwales/gaius/games/ptower.html) `<http://floppsie.comp.glam.ac.uk/Southwales/gaius/games/ptower.html>`